Scratch: Installation for Finch 1



The future of Scratch 2.0 offline and ScratchX is uncertain.

We encourage you to use Snap! with your Finch Robot to ensure long-term support.

Scratch is a tile-based visual programming language, which is an excellent first language for children to learn. We are providing a helper app that allows you to use Scratch 2.0 with Finch and Hummingbird.

TABLE OF CONTENTS

$\mathbf{0}$

- Download & Install
- Launching Scratch
- Finch Block Descriptions
- Known Issues and Troubleshooting

Download & Install

Windows

<u>Download the Windows installer</u> and double click on it. Follow the instructions in the installer. Once installation is complete, a short cut to BirdBrain Robot Server will appear on your desktop. Finch's Scratch library currently only works with Scratch 2.0's offline editor. <u>Install it from here.</u>

Mac

Scratch 2.0 offline cannot be installed with MacOS Catalina. We recommend you use <u>Snap!</u> instead.

If you installed Scratch 2.0 offline before 2020, your Mac computer may still be able to run Scratch 2.0 offline with the BirdBrain Robot Server. If that is the case, download the BirdBrain Robot Server here. Another potential alternative is to install the Chromebook app on your Mac instead by following the Chromebook instructions below, but Google plans to discontinue the use of Chromebook apps on Mac and Windows computers in June 2021. Snap! is a better long-term solution.

Chromebook


Visit the Chrome webstore to install the <u>Finch Connection App</u>. You do not need to install Scratch 2.0 offline if using a Chromebook, as we use the <u>ScratchX</u> website instead.

Important Note: Projects saved on a Chromebook will not work with the BirdBrain Robot server used on Windows or Mac.

KNOWN ISSUES AND TROUBLESHOOTING

Launching Scratch


Launching Scratch with Finch – Windows and Mac



At present, the Finch only works with the <u>Scratch 2.0 off-line editor</u>. Once you have installed the editor and the BirdBrain Robot Server, do the following: Plug in a Finch.

Start the BirdBrain Robot Server helper application. It should show that the Finch is connected. Start Scratch 2.0 by clicking on "Open Scratch" in the BirdBrain Robot Server. In Windows and Mac, the Finch blocks will show up in the "More Blocks" category.

Loading Finch Blocks Manually



file containing the Finch and Hummingbird extensions, as well as a few example programs. Import the Finch Extension file (finch.s2e). Hold down the Shift key and click on File at the top left hand corner of the page. You should see the following:

The Finch blocks will now be in the More Blocks category.

Launching Scratch with Finch - Chrome OS



Plug in the Finch

Launch the Finch Connection App:

Click the Open Scratch button on the app to automatically load a ScratchX page with the Finch blocks loaded, and accept any prompts when the page loads. Click Enable Flash if needed. If the ScratchX interface with Finch blocks doesn't load, you can access it directly here or click Open Extension URL and then enter the URL for the Finch:

http://birdbraintechnologies.github.io/Chrome-Scratch-and-Snap-Support/Scratch%20Plugins/FinchHID_Scratch(Chrome%20Plugin).js

Finch Block Descriptions

Motor Commands

 Move Finch left: right: Sets the power to the left and right wheels. The range is -100 to 100; for example Move Finch left: 100 right: 100 is full forward, left: -100 right: -100 is full backwards.

LED Commands

• Finch LED color R: G: B: Sets the color of the Finch's beak. The R, G, and B arguments control the intensity of the red, green, and blue elements in the Finch's beak. Range is 0 to 100 for each color.

Sound Commands

• Finch buzz at Hz ms: Plays the Finch's buzzer with a sound of the frequency specified for the time specified. Range is 20 to 20,000 for frequency.

Sensing Commands


- Finch temperature: Returns the current temperature in Celsius.
- Finch left light and right light: Returns the intensity of light hitting the left or right light sensor. The values are in a range from 0 to 100 where 0 is total darkness and 100 is saturation of the sensor.
- Finch left and right obstacle: These are boolean or predicate blocks, returning true if an object is 1-4" from the sensor and false otherwise.
- Finch X/Y/Z Acceleration: Returns the current g-forces measured along the Finch's X (beak to tail), Y (wheel to wheel), and Z (top to bottom) axes. Range is -1.5 to 1.5 gees.
- Finch Orientation: Returns the current orientation of the Finch. Possible responses are Level, Upside Down, Beak Up, Beak Down, Left Wing Down, Right Wing Down, and In Between.

Speak Block

• The Speak block will cause the computer to say whatever text is placed in the box.

Known Issues and Troubleshooting

- Loops with just Finch command blocks seem to run just once instead of looping. Add a
 non Finch/Hummingbird block into the loop to make the loop work (a good dummy block
 is a "Wait 0").
- If you are running an older version of the Birdbrain Robot Server (downloaded prior to May 2017), the sensor values may update very slowly. This is caused by App Nap putting the BirdBrain Robot Server to sleep. We recommend that you uninstall the Birdbrain Robot Server and install the most recent version. To manually disable App Nap on the BirdBrain Robot Server, CTRL-click on the BirdBrain Robot Server application and select Get Info in the resulting menu. In the Info window, check the box for Prevent App Nap:



• In Mac, if both Finch and Hummingbird are plugged in, you may see a 5-10 second delay after you try closing the server, and you may get an error message on close.

- In Mac, occasionally the application will not quit when you try to close the window end the process with force quit.
- If the robot seems to stop responding for any reason, there is no need to close Scratch. Close the BirdBrain Robot Server application instead and re-open it.
- If the "Open Scratch" button on the BirdBrain Robot Server does not open Scratch, or opens Scratch without the Finch blocks loaded, you can <u>load the Finch extension file</u> manually.
- The Finch Connection App for Chrome must stay visible on the desktop if using it with a Macbook running OS 10.9 or later. If the app is minimized, sensor values will stop updating and output commands will be sent very slowly.